

## Table des matières



- On récupère les infos sur le lecteur et sa bande

```
root@server2898:/tmp$ mt status
Drive:  HP C5683A
Format: DDS-3 format
Status: [41112500] B0T online compression immediate-report-mode
File:    0
Block:   0
```

- On check les devices de type tape.

```
root@server2898:/tmp$ /usr/sbin/ioscan -C tape -fun
Class      I  H/W Path      Driver   S/W State   H/W Type   Description
=====
tape       0  2/0/1/1/0/4/1.0.0  stape    CLAIMED     DEVICE      HP          C5683A
                /dev/rmt/0m      /dev/rmt/0mnb /dev/rmt/clt0d0BESTn /dev/rmt/clt0d0DDsb
                /dev/rmt/0mb      /dev/rmt/clt0d0BEST /dev/rmt/clt0d0BESTnb /dev/rmt/clt0d0DDSn
                /dev/rmt/0mn      /dev/rmt/clt0d0BESTb /dev/rmt/clt0d0DDS  /dev/rmt/clt0d0DDSnb
```

- On fait un test de sauvegarde :

```
root@server2898:/tmp$ /usr/bin/tar cvf /dev/rmt/c0t3d0BEST /etc/passwd
a /etc/passwd 4 blocks
```

- On regarde si tout est OK :

```
root@server2898:/tmp$ /usr/bin/tar tvf /dev/rmt/c0t3d0BEST /etc/passwd
r--r--r--  0/0  1857 Sep  4 00:31 2007 /etc/passwd
```

- On lance la sauvegarde :

```
/opt/ignite/bin/make_recovery -v -C -A -d /dev/rmt/0mn
```

ou

```
/opt/ignite/bin/make_tape_recovery -x inc_entire=vg00
```

From:  
<https://unix.ndlp.info/> - **Where there is a shell, there is a way**

Permanent link:  
[https://unix.ndlp.info/doku.php/informatique:nix:hp:hpux\\_basic\\_admin:utiliser\\_les\\_bandes](https://unix.ndlp.info/doku.php/informatique:nix:hp:hpux_basic_admin:utiliser_les_bandes)

Last update: **2009/06/29 19:04**