

**Table des matières**

Gen8 - upgrade bios & ILO .....	3
Fichiers .....	3



## Gen8 - upgrade bios & ILO

### Fichiers

- BIOS (01/22/2018)

[bios\\_SP99233.exe](#) ⇒ extraire le fichier `SP99233.exe\ROMPaq Flat Files\CPQJ0613.436`

- ILO 2.77(17 Dec 2020)

[ilo\\_cp046021.exe](#) ⇒ extraire le fichier `cp046021\ilo4_277.bin`

- Flasher via l'ILO ⇒ prise en compte lors du prochain reboot

**ILO 4**  
Firmware Update

Type	Date	Version
ILO	Dec 17 2020	2.77

**Firmware Update**  
ILO Firmware

Obtain the firmware image (.bin) file from the Online ROM Flash Component for HPE ILO 4

- The latest component can be downloaded from <http://www.hpe.com/support/ilo4>.
- This component is also available on the HPE Service Pack.

**Server Firmware**

The following types of server firmware can also be updated from this page:

- HPE System ROM
- System Programmable Logic Device
- SLO Chassis Firmware

Server firmware files can be obtained from <http://www.hpe.com/support/ilo4>. For more information, please see the help file.

Local File: Update the firmware by uploading a local file. Note: Navigating away from this page before the upload has completed will prevent the update from starting.

File:  Aucun fichier choisi

### Annexes

- [https://support.hpe.com/hpsc/swd/public/detail?swItemId=MTX\\_671606ca210640bb93ae3b683](https://support.hpe.com/hpsc/swd/public/detail?swItemId=MTX_671606ca210640bb93ae3b683)
- <https://support.hpe.com/hpsc/swd/public/detail?swItemId=MTX-2a4f6e276e9d4eac9d3716e50b>

From:  
<https://unix.ndlp.info/> - Where there is a shell, there is a way

Permanent link:  
[https://unix.ndlp.info/doku.php/blog:gen8\\_-\\_upgrade\\_bios\\_ilo](https://unix.ndlp.info/doku.php/blog:gen8_-_upgrade_bios_ilo)

Last update: 2021/04/04 09:02